


SEASIDE DREAMS

Table Set



Featuring fabrics from the **Seaside Dreams** collection by **Sharla Fults** for 

Runner Fabric Requirements

(A) 3431P-90	1 3/8 yards
(B) 3428-90	7/8 yard
(C) 1351-Stone**	1/3 yard
(D) 3432-16	1/4 yard
(E) 3430-76	5/8 yard
(F) 3051-09	1/2 yard*
Backing	
3432-44	2 1/8 yards

Place Mat Fabric Requirements (Makes 4)

(A) 3431P-90	3/4 yard
(B) 3428-40	5/8 yard
(C) 3428-90	1 1/2 yards*
(D) 3430-76	1/4 yard
(E) 3432-16	3/8 yard
Backing	
3430-40	1 1/2 yards

* Includes Binding

** Just Color! Collection

Additional Supplies Needed

Batting (1) 72" x 36", (4) 26" x 21"
 Piecing and sewing thread
 Quilting and sewing supplies

Quilt designed by Heidi Pridemore
 Finished Runner Size 64" x 28"
 Finished Place Mat Size 22" x 17"
 Skill Level: Advanced Beginner

Runner - Cutting

Runner Cutting Instructions

Please note: All strips are cut across the width of fabric (WOF) from selvage to selvage edge unless otherwise noted.

WOF= Width of Fabric • LOF = Length of Fabric

Fabric A (3431P-90 Seaside Boxes - Grey):

- Fussy cut (1) 48 ½" x 12 ½" strip (3 boxes by 12 boxes).

Fabric B (3428-90 Tonal Coral & Shells - Grey), cut:

- (1) 3" x WOF strip, sub-cut (2) 3" x 12 ½" strips.
- (3) 3" x WOF strips. Sew the strips together end to end with diagonal seams and cut (2) 3" x 53 ½" strips.
- (2) 2 ½" x 24 ½" WOF strips.
- (4) 2 ½" x WOF strips. Sew the strips together end to end with diagonal seams and cut (2) 2 ½" x 64 ½" strips.

Fabric C (1351-Stone Just Color! - Stone), cut:

- (4) 2" x WOF strips, sub-cut (72) 2" squares.

Fabric D (3432-16 Sand Dollars - Aqua), cut:

- (1) 4 ½" x WOF strip, sub-cut (6) 4 ½" squares.

Fabric E (3430-76 Packed Shells - Teal), cut:

- (4) 4 ½" x WOF strips, sub-cut (32) 4 ½" squares.

Fabric F (3051-09 Brushstrokes - Pewter), cut:

- (5) 2 ½" x WOF strips for the binding.

Backing (3432-44 Sand Dollars - Dark Ecrú), cut:

- (1) 72" x 36" WOF strip for the back.

Runner - Sewing

Sew using a $\frac{1}{4}$ " seam allowance with right sides together (RST) unless otherwise indicated. Always press towards the darker fabric while assembling, unless otherwise noted by the arrows.

Block Assembly

1. Sew (1) $3'' \times 12\frac{1}{2}''$ Fabric B strip to each side of the $48\frac{1}{2}'' \times 12\frac{1}{2}''$ Fabric A strip. Sew (1) $3'' \times 53\frac{1}{2}''$ Fabric B strip to the top and to the bottom of the Fabric A strip. Trim the block to measure $52\frac{1}{2}'' \times 16\frac{1}{2}''$ to make the Center Block (Fig. 1).




Fig. 1

2. Place (1) $2''$ Fabric C square on the top left corner of (1) $4\frac{1}{2}''$ Fabric D square, right sides together (Fig. 2). Sew across the diagonal of the smaller square from the upper right corner to the lower left corner (Fig. 2). Flip open the triangle formed and press (Fig. 3). Trim away the excess fabric from behind the triangle $\frac{1}{4}''$ away from the sewn seam.

3. Follow Figure 4 for the seam direction to add a $2''$ Fabric C square to the upper right corner of the $4\frac{1}{2}''$ Fabric D square to make (1) CDC block (Fig. 5).

4. Repeat Steps 2-3 to make a second CDC block.




Fig. 2

Fig. 3

Fig. 4

Fig. 5

5. Repeat Steps 2-3 using (64) $2''$ Fabric C squares and (32) $4\frac{1}{2}''$ Fabric E squares to make (32) CEC blocks (Fig. 6).

6. Place (1) $2''$ Fabric C square on the top left corner of (1) $4\frac{1}{2}''$ Fabric D square, right sides together. Sew across the diagonal of the smaller square from the upper right corner to the lower left corner. Flip open the triangle formed and press. Trim away the excess fabric from behind the triangle $\frac{1}{4}''$ away from the sewn seam to make (1) CD block (Fig. 7). Repeat to make (4) CD blocks total.




Fig. 6




Fig. 7

Runner Top Assembly

(Follow Figure 8 while assembling the runner top.)

7. Sew (4) CEC blocks together. Repeat to make a second strip. Sew (1) strip to each side of the Center Block. Pay attention to the orientation of the blocks.

8. Sew (6) CEC blocks together to make (1) CEC strip. Repeat to make (4) CEC strips total.

9. Sew (1) CD block, (1) CEC strip, (1) CDC block, (1) CEC strip and (1) CD block together, in that order, to make (1) strip. Repeat to make a second strip. Sew the strips to the top and to the bottom of the Center Block. Pay attention to the orientation of the blocks.

10. Sew (1) 2 ½" x 24 ½" Fabric B strip to each side of the Center Block. Sew (1) 2 ½" x 64 ½" Fabric B strip to the top and to the bottom of the Center Block to make the runner top.

Layering, Quilting and Finishing

11. Press the runner top and 72" x 36" backing well. Layer backing (wrong side up), batting, pressed quilt top (right side up) and baste. Quilt as desired and trim excess batting and backing when quilting is complete.

Binding

12. Cut the ends of the (5) Fabric F binding strips at a 45-degree angle and sew end to end to make (1) continuous piece of binding. Fold in half lengthwise and press wrong sides together.

13. Sew the binding to the front of the runner; raw edges together. Turn the folded edge to the back, and hand stitch in place.




Fig. 8

Place Mat - Cutting

Place Mat Cutting Instructions

Please note: All strips are cut across the width of fabric (WOF) from selvage to selvage edge unless otherwise noted.

WOF= Width of Fabric • LOF = Length of Fabric

Fabric A (3431P-90 Seaside Boxes - Grey):

- Fussy cut (4) 12 ½" squares (3 boxes by 3 boxes).

Fabric B (3428-40 Tonal Coral & Shells - Ecrú), cut:

- (3) 2" x WOF strips, sub-cut (8) 2" x 12 ½" strips.
- (4) 2 ½" x WOF strips, sub-cut (8) 2 ½" x 15 ½" strips.

Fabric C (3428-90 Tonal Coral & Shells - Grey), cut:

- (4) 1 ½" x WOF strips, sub-cut (8) 1 ½" x 15 ½" strips.
- (8) 1 ½" x 22 ½" WOF strips.
- (4) 1 ¾" x WOF strips, sub-cut (80) 1 ¾" squares.
- (9) 2 ½" x WOF strips for the binding.

Fabric D (3430-76 Packed Shells - Teal), cut:

- (1) 3 ½" x WOF strip, sub-cut (8) 3 ½" squares.

Fabric E (3432-16 Sand Dollars - Aqua), cut:

- (3) 3 ½" x WOF strips, sub-cut (32) 3 ½" squares.

Backing (3430-40 Packed Shells - Ecrú), cut:

- (2) 26" x WOF strips, sub-cut (4) 26" x 21" strips for the backs.

Place Mat - Sewing

Sew using a ¼" seam allowance with right sides together (RST) unless otherwise indicated. Always press towards the darker fabric while assembling, unless otherwise noted by the arrows.

Block Assembly

1. Sew (1) 2" x 12 ½" Fabric B strip to each side of (1) 12 ½" Fabric A square. Sew (1) 2 ½" x 15 ½" Fabric B strip to the top and to the bottom of the Fabric A square. Trim the block to measure 14 ½" x 15 ½" to make (1) Center Block (Fig. 9). Repeat to make (4) Center Blocks total.





Fig. 9


2. Place (1) $1\frac{3}{4}$ " Fabric C square on the top left corner of (1) $3\frac{1}{2}$ " Fabric D square, right sides together (Fig. 10). Sew across the diagonal of the smaller square from the upper right corner to the lower left corner (Fig. 10). Flip open the triangle formed and press (Fig. 11). Trim away the excess fabric from behind the triangle $\frac{1}{4}$ " away from the sewn seam.

3. Follow Figure 12 for the seam direction to add a $1\frac{3}{4}$ " Fabric C square to the upper right corner of the $3\frac{1}{2}$ " Fabric D square to make (1) CDC block (Fig. 13).

4. Repeat Steps 2-3 to make (8) CDC blocks total.



5. Repeat Steps 2-3 using (64) $1\frac{3}{4}$ " Fabric C squares and (32) $3\frac{1}{2}$ " Fabric E squares to make (32) CEC blocks (Fig. 14).



Place Mat Tops Assembly

(Follow Figure 15 while assembling the place mat tops.)

6. Sew (2) CEC blocks, (1) CDC block and (2) CEC blocks together, in that order, to make (1) side strip. Repeat to make (8) side strips.

7. Sew (1) side strip to each side of (1) Center Block. Repeat with the remaining (6) side strips and (3) Center Blocks.

8. Sew (1) $1\frac{1}{2}$ " x $15\frac{1}{2}$ " Fabric C strip to each side of the (1) Center Block. Sew (1) $1\frac{1}{2}$ " x $22\frac{1}{2}$ " Fabric C strip to the top and to the bottom of the Center Block to make (1) Place Mat top. Repeat to make (4) Place Mat tops total.

Layering, Quilting and Finishing

9. Press the place mat tops and 26 " x 21 " backings well. Layer backings (wrong side up), battings, pressed quilt tops (right side up) and baste. Quilt as desired and trim excess batting and backing when quilting is complete.

Binding

10 Cut the ends of the (9) Fabric C binding strips at a 45-degree angle and sew end to end to make (1) continuous piece of binding. Fold in half lengthwise and press wrong sides together. Cut the long strip into (4) equal lengths.

11. Sew the binding to the front of the place mat, raw edges together. Turn the folded edge to the back, and hand stitch in place.




Fig. 15